

Capture



Product Intro

Welcome to **Trimble Forensics** Capture. This document is meant to help you learn the new features and functionality found within Trimble Capture. If you have additional questions please refer to our support team.

Scene list

Menu


Opens application settings

Scene

Represents a scene the user already has existing. Click on the scene to open it in the editor

Create new Scene

This creates a new scene and initiates the new scene wizard



Sort Options

Quickly toggle between different sort types to view your scenes.

Sort Options

Brings up alternate options for the given scene including share, delete and notes

The main screen allows the user access to their created scenes as well as the ability to create new scenes. Capture offers added functionality in terms of managing and exporting your scenes to other platforms.

Menu



Menu



Options

Change and configure system options and settings

Connect Login

Sign in to your trimble connect account

About


Access your Capture version information and licensing details

The menu screen allows the user to change and alter system settings as well as login to their Trimble Connect account. Also the user can access their license information and capture version data.

Scene Options



Scene Options



The image shows a yellow smartphone screen displaying a list of scene entries. The screen has a dark background with white text. At the top, there are sorting options: 'Date Modified', 'Newest - Oldest', and 'Oldest - New'. The list contains four entries, each with a title, a date and time, and a three-dot menu icon. The entries are: 'musee scene at museum', 'car accident 2 - highway', 'car accident - intersection (Paul road)', and 'Crime scene - warehouse'. At the bottom of the screen, there is a white bar with three icons: a book icon labeled 'Notes', a share icon labeled 'Share', and a trash can icon labeled 'Delete'. Red lines connect these icons to their respective text descriptions on the left and right sides of the phone.

Notes
Add notes to your scene that get exported when brought into Trimble Reveal

Share
Quickly email, or sync you file to available file sharing or cloud services

Delete
Allows the user to delete the chosen scene

Scene options allows the user access to advanced options when attempting to share, or record data for themselves or when exporting to other Trimble Products. This is also where the user deletes a chosen scene.

New Scene




Measurement

Choose whether or not you want to use a total station or measure manually



Choose your model

Select the make and model of your total station. Click the right arrow to proceed.



Connection Settings

Choose your connection type and keep in mind that the connection type may alter the proceeding screens for the rest of the scene setup.

There are a lot of things to consider when creating a new scene, but make sure before you begin that you know what make and model your total station is, and what type of connection setting you wish to use. Click the arrows as you proceed to move onto the next stage of the process.

Editor

Scene Menu

Access connection settings, save/close functions and other options relevant to the scene.

View Options

Toggle 2d, 3d or Vision mode as well as the available grid option. Also allows the user to undo previous actions.

Current Point Code

Toggle Point Codes on or off and click to change current Point Code

Current Line


Toggle lines on or off and click to change current line

New Point

Initiate a new point. Click this button to place a new point at a chosen location on the canvas.

Point Count

Keeps track of next shot you are about to shoot.



The main editor contains all the tools for the user to shoot and record points within their scene. Point codes and lines will appear when they have been toggled on by the user using the appropriate buttons located in the lower corners of the screen.

New Point



New Point

Cancel

Click here to cancel the current point and return to the scene editor.

Evidence Marker

Attaching an evidence marker labels it on the scene and allows the user to attach images and notes to a point.

14 97 08:39

✕ Add New Point ✓

Point 1

X Value 0.00ft Y Value 0.00ft

Elevation 0.00ft

Point Code

() Edit Current Point Code

🚩 Attach Evidence Marker

Add to Line

<NEW>

Confirm Point

When you are happy your point, click confirm to place it on the scene.

Add to Line

If current line was not turned on in the editor click here to add the point to a new or existing line

When adding a new point using a total station the position will be pre-populated. Additionally, the user can configure capture to not show this screen at all when using a total station within the application configurations in the menu.